
ATA SNAP Firmware Manual

Release 1.0.2

Jack Hickish

Sep 16, 2020

CONTENTS:

1	ATA SNAP F-Engine Firmware User Manual	1
1.1	Introduction	1
1.1.1	Spectrometer Mode	1
1.1.2	Voltage Mode	2
1.1.3	This Document	2
1.2	Output Data Formats	2
1.2.1	Spectrometer Packets	2
1.2.2	Voltage Packets	3
1.3	Hardware Overview	4
1.4	Firmware Overview	6
1.4.1	Building the Simulink Model	6
1.4.2	Firmware Overview	7
1.4.3	Module Descriptions	8
1.4.3.1	ADC	8
1.4.3.2	Filter Bank	8
1.4.4	Spectral Power Accumulator	10
1.4.5	Equalization	11
1.4.6	Voltage Channel Selection	11
1.4.7	10Gb Ethernet	11
1.4.8	Spectral Power Accumulator	11
1.5	Run-time Control	11
1.5.1	Installing the Control Library	11
1.6	Configuration Recipes	12
1.6.1	Configuration File	13
2	ata_snap API reference	15
3	Index	21
	Bibliography	23
	Python Module Index	25
	Index	27

ATA SNAP F-ENGINE FIRMWARE USER MANUAL

1.1 Introduction

This repository contains firmware and software for a SNAP-based F-Engine (i.e. channelizer) system for the Allen Telescope Array (ATA).

The system digitizes RF signals from the ATA at a speed, f_s , of up to 2500 Msps and generates 4096 frequency channels over the Nyquist band. Two operational modes are supported: *Spectrometer* mode, and *Voltage* mode. These different modes, shown in a high-level block diagram in Fig. 1.1, apply different processing to the channelizer output prior to outputting data over 10 gigabit Ethernet (10GbE).




Fig. 1.1: The ATA SNAP F-Engine firmware comprises two pipelines. One of these – the *Spectrometer* pipeline – generates accumulated power spectra. The other – the *Voltage Pipeline* – generates a complex voltage stream channelized into 2048 frequency bins.

1.1.1 Spectrometer Mode

In *Spectrometer* mode, integrated power spectra are generated by the SNAP Firmware. The resolution of these spectra, f_c , is $\frac{f_s}{8192}$. At maximum sampling rate, $f_s = 2500$ Msps, resulting in a spectra resolution $f_c = 305$ kHz.

Spectra are generated for both the X- and Y-polarizations, which are formatted as an f_c -element array of 32-bit signed integers. A cross-power spectra, defined as the multiple of an X-polarization spectra with the complex conjugate of a Y-polarization spectra, is also computed. This is formatted as an f_c -element array of 32-bit complex (i.e. 32-bit real, 32-bit imaginary) signed integers.

Data are accumulated for a runtime-configurable number of spectra, and are output from the firmware as a UDP data stream over a 10 Gb Ethernet link. The output format is described in detail in [Output Data Formats](#).

1.1.2 Voltage Mode

In *Voltage* mode, up to 2048 frequency channels - each with a resolution of $\frac{f_s}{8192}$ - are output over a 10 Gb Ethernet link.

In this mode, data are transmitted as complex, signed, 4-bit integers over a UDP data stream.

1.1.3 This Document

This document describes the hardware configuration required by the F-Engine system, the runtime configuration procedures, and the software control functionality made available to the user. It also provides a description of the output data formats of each of the two data processing modes.

1.2 Output Data Formats

1.2.1 Spectrometer Packets

In versions 1.0.x of the SNAP firmware, each spectrometer dump is a 64 kiB data set, comprising 4096 channels and 4 32-bit words per channel. Each data dump is transmitted from the SNAP in 8 UDP packets, each with an 512 channel (8 kiB) payload and 8 byte header:

```
#define N_c 512
#define N_p 4

struct spectrometer_packet {
    uint64 header;
    int32 data[N_c, N_p]
};
```

The header should be read as a network-endian 64-bit unsigned integer, with the following bit fields:

- bits[7:0] (i.e. `header & 0xff`): 8-bit antenna ID
- bits[10:8] (i.e. `(header >> 8) & 0x7`): 3-bit channel block index
- bits[55:11] (i.e. `(header >> 11) & 0x1fffffffffffff`): 45-bit accumulation ID
- bits[63:56] (i.e. `(header >> 56) & 0xff`): 8-bit firmware version

Headers fields should be interpreted as follows:

- *Antenna ID*: A runtime configurable ID which uniquely associates a packet with a particular SNAP board and antenna. See TODO
- *Channel block index*: Indicates which channels are in this packet. A value of b indicates that this packet contains channels $512b$ to $512(b + 1)$.
- *Accumulation ID*: A counter that represents the integration number. I.e., the first integration will have an ID 0, the second and ID 1, etc. These IDs should be referred to GPS time through knowledge of the system sampling rate and accumulation length parameters, and the system was last synchronized (see TODO).
- *Firmware version*: Bit [7] is always 0 for *Spectrometer* packets. The remaining bits contain a compile-time defined firmware version, represented in the form `bit[6].bits[5:3].bits[2:0]`. This document refers to firmware version 1.0.2.

The data payload in each packet should be interpreted as an 8192 byte array of network-endian 32-bit integers with dimensions `channel` x `polarization-product`. The `channel` index runs from 0 to 511. The `polarization-product` index runs from 0-3 with:

- index 0: *XX* product
- index 1: *YY* product
- index 2: *real* part of *XY** product
- index 3: *imag* part of *XY** product

1.2.2 Voltage Packets

The *Voltage* mode of the SNAP firmware outputs a continuous stream of voltage data, encapsulated in UDP packets. Each packet contains a data payload of 8192 bytes, made up of 16 time samples for 256 frequency channels of dual-polarization data:

```
#define N_t 16
#define N_c 256
#define N_p 2

struct spectrometer_packet {
    uint64 header;
    int32 data[N_t, N_c, N_p]
};
```

The header should be read as a network-endian 64-bit unsigned integer, with the following bit fields:

- bits[5:0] (i.e. `header & 0x3f`): 6-bit antenna ID
- bits[17:6] (i.e. `(header >> 6) & 0xffff`): 12-bit channel number
- bits[55:18] (i.e. `(header >> 18) & 0x3fffffffff`): 38-bit sample number
- bits[63:56] (i.e. `(header >> 56) & 0xff`): 8-bit Firmware version

Headers fields should be interpreted as follows:

- *Antenna ID*: A runtime configurable ID which uniquely associates a packet with a particular SNAP board and antenna. See `TODO`
- *Channel number*: The index of the first channel present in this packet. For example, a channel number *c* implies the packet contains channels *c* to *c* + 255.
- *Sample number*: The index of the first time sample present in this packet. For example, a sample number *s* implies the packet contains samples *s* to *s* + 15. Sample number can be referred to GPS time through knowledge of the system sampling rate and accumulation length parameters, and the system was last synchronized (see `TODO`).
- *Firmware version*: Bit [7] is always 1 for *Voltage* packets. The remaining bits contain a compile-time defined firmware version, represented in the form `bit[6].bits[5:3].bits[2:0]`. This document refers to firmware version 1.0.2.

Note that at full sample rate (2500 Msps) spectra are generated every 3.2 microseconds, thus a 38-bit spectra counter will roll over every ~10 days. Downstream software should take account of this if the system is expected to run for longer than this duration without a new synchronization trigger (see `TODO`)

The data payload in each packet is 8192 bytes. Each bytes of data should be interpreted as a 4-bit complex number (i.e. 4-bit real, 4-bit imaginary) with the most significant 4 bits of each byte representing the real part of the complex sample, and the least significant 4 bits representing the imaginary part of the complex sample.

The complete payload is an array with dimensions `time x channel x polarization`, with

- `time` index running from 0 to 15
- `channel` index running from 0 to 255
- `polarization` index running from 0 to 1 with index 0 representing the X-polarization, and index 1 the Y-polarization.

1.3 Hardware Overview

A pair of analog inputs to the SNAP system are digitized with a CASPER-designed *ADC5g* ADC card [[casper_adc5g](#)] which hosts a single e2v EV8AQ160 chip [[e2v](#)]. The EV8AQ160 is a cost-effective 8-bit, quad-channel, 1250 Msps ADC, which can be configured to run as a dual-channel 2500 Msps, or single-channel 5000 Msps digitizer. The ATA system uses dual-channel configuration, with each *ADC5g* card processing dual polarization inputs from a single dish.

Digital signal processing is performed using a CASPER-designed SNAP board [[casper_snap](#)]. The SNAP is a simple FPGA-based processor, featuring a low-cost Kintex 7 FPGA, and a pair of SFP+ connectors each capable of supporting a 10-Gb Ethernet link. In addition to the FPGA, the SNAP hosts three on-board Hittite HMCAD1511 ADC chips [[hmcad1511](#)], which are not used in the ATA deployment owing to their relatively low sampling rate.

SNAPs and their ADCs are housed in a custom-designed 1U enclosure, shown in [Fig. 1.2](#) and [Fig. 1.3](#). This box also houses a Raspberry Pi 2 Model B [[rpi](#)] which provides the ability to remotely program and interact with a SNAP board.



Fig. 1.2: The custom-designed 1U SNAP enclosure front panel. Interfaces (left to right): A pair of 10GbE-capable SFP+ ports; SMA input for a trigger signal; SMA output for a trigger signal; SMA input for onboard-ADC reference clock (not used at the ATA); SMA inputs for onboard-ADC sample clock (not used at the ATA); SMA inputs for 12 on-board ADC channels (not used at the ATA); four SMA inputs routed to the *ADC5G* card – dual RF inputs, a sampling clock, and a trigger signal; RJ45 1GbE interface routed to an internal Raspberry Pi single-board computer; 110-230V AC power.

The complete ATA system, comprising multiple boards, should be driven by a common sampling clock, at a maximum rate of 2500~Msps. Each board should also be fed with a time-aligned trigger signal, which is used to synchronize the the capture of data by different boards in the system.




Fig. 1.3: Internal wiring of the ATA SNAP enclosure. Not shown is a Raspberry Pi control computer, whose mount holes are visible to the upper-right of the SNAP board. RF anti-aliasing filters are visible on the ADC analog RF inputs. These may be removed if upstream filtering is present in the system.

1.4 Firmware Overview

The firmware described in this document is designed in Mathwork's Simulink using CASPERs FPGA programming libraries. The Simulink source file is available [on github](#).

1.4.1 Building the Simulink Model

The SNAP firmware model (`snap_adc5g_feng_rpi.slx`) was built with the following software stack. Use other versions at your peril.

- Ubuntu 18.04 64-bit
- MATLAB/Simulink 2019a, including Fixed Point Designer Toolbox
- Xilinx Vivado System Edition 2019.1.3
- `mlib_devel` (version controlled within the `ata_snap` repository).

To obtain and open the Simulink model:

```
# Clone the firmware repository
git clone https://github.com/realtimeradio/ata_snap

# Clone relevant sub-repositories
cd ata_snap
git submodule init
git submodule update

# Install the mlib_devel dependencies
# You may want to install these in a Python virtual environment
cd mlib_devel
pip install -r requirements.txt
```

Next, create a local environment specification file in the `ata_snap` directory, named `startsg.local`. An example environment file is:

```
#!/bin/bash
##### User to edit these accordingly #####
export XILINX_PATH=/data/Xilinx/Vivado/2019.1
export MATLAB_PATH=/data/MATLAB/R2019a
# PLATFORM lin64 means 64-bit Linux
export PLATFORM=lin64
# Location of your Xilinx license
export XILINXD_LICENSE_FILE=/home/jackh/.Xilinx/Xilinx.lic

# Library tweaks
export LD_PRELOAD=${LD_PRELOAD}:/usr/lib/x86_64-linux-gnu/libexpat.so"
# An optional python virtual environment to activate on start
export CASPER_PYTHON_VENV_ON_START=/home/jackh/casper-python3-venv
```

You should edit the paths accordingly.

To open the firmware model, from the top-level of the repository (i.e. the `ata_snap` directory) run `./startsg`. This will open MATLAB with appropriate libraries, at which point you can open the `snap_adc5g_feng_rpi.slx` Simulink model.

1.4.2 Firmware Overview

The Simulink source code for the SNAP firmware is shown in Fig. 1.4. A pictorial representation with annotated data path bit widths is shown in Fig. 1.5.




Fig. 1.4: The snap_adc5g_feng_rpi.slx Simulink design, with annotations.




Fig. 1.5: A pictorial representation of the SNAP firmware, showing major processing modules and the bit widths of their data paths. Yellow circles in this diagram represent the runtime-controllable elements of the pipeline.

In the remainder of this section an overview of the functional modules in the system is given.

1.4.3 Module Descriptions

Here basic explanations of the functionality of the different firmware processing modules is given. Where modules can be controlled or monitored at runtime, software routines to do so are described in *Run-time Control*.

1.4.3.1 ADC

The ADC module encapsulates an interface to an e2v EV8AQ160 [e2v] ADC chip. This chip has four independent ADC cores which can each run at up to 1250 Msps. In the ATA firmware, these are configured as a pair of 2500 Msps samplers.

On power-up, and after reprogramming the FPGA, the ADC interface must be initialized. Initialization ensures that the ADC is in the correct operating mode, and that the ADC and FPGA link is appropriately trained. Training ensures that the digital data transmitted from the ADC is successfully received by the FPGA, and involves tweaking the FPGA-side capture clock phase for reliable data reception.

To ensure that the ADCs are correctly configured when programming the SNAP boards, the boards should always be loaded with firmware using the `program` method (see *Run-time Control*).

TODO: Add software method and instructions for inter-core mismatch calibration.

Relevant Software Methods

- `program`: Load new firmware onto a SNAP and initialize the ADCs
- `adc_initialize`: Perform a standalone initialization of the ADCs
- `adc_get_samples`: Get a snapshot of raw ADC samples
- `adc_get_stats`: Get the mean, mean power, and number of clipping events from the last 512k samples

1.4.3.2 Filter Bank

The Filter Bank (aka Polyphase Filter Bank, PFB [pfb]) separates the X- and Y-polarization input broad-band data streams into 4096 frequency channels, starting at DC, with centers separated by $\frac{f_s}{4096}$. These baseband frequencies, from DC to $\frac{f_s}{2}$ represent different sky-frequencies when the input analog signals are mixed with LOs upstream of the digital system.

As shown in Fig. 1.5, the PFB receives real-valued broad-band data with 8-bits resolution, and after processing delivers complex-valued spectra with 18-bit resolution.

Internally, the FFT processes data at a precision of 25 bits, allowing for significant growth in the required dynamic range of the narrow-band signals. The internal data path is shown, with relevant data bit width, in Fig. 1.6.

Critical for effective operation of the PFB is the application of an appropriate FFT *shift schedule*. The shift schedule controls, for each butterfly stage of the FFT, whether data are allowed to grow, or should be divided by two to prevent overflows. In general, an FFT with 2^N points has N butterfly stages, and dynamic range should grow by N bits to guarantee against overflow. Allowing such large bitgrowth is resource-intensive, so scaling down data to prevent overflow can be a useful alternative.

The SNAP firmware processes 18-bit inputs with 25-bits of precision, allowing for 7 bits of growth. A further scaling down of 2^6 using the shift schedule is sufficient to guarantee against overflow. It is therefore recommended that the shift schedule is set to scale by at least this much.

After the FFT, the data path is scaled back to 18 bits to facilitate cheaper downstream processing. This scaling is implemented by saturating the input signal if it exceeds the range permitted by an 18-bit representation.




Fig. 1.6: A pictorial representation of the PFB internal datapath, showing internal data precision. Coefficients in the FIR and FFT modules are stored with 18 bits resolution. Overall signal amplitude growth is controlled with a runtime-applied *shift schedule*, and monitoring allows for overflows at two stages of the PFB pipeline to be detected.

Software routines are provided to count the number of overflows both within the FFT module, and in the post-FFT saturation logic.

Note that saturation events in the FFT should be absolutely avoided (and preferably the shift schedule should be chosen so as to make them impossible) since these corrupt entire FFT frames. Saturation events in the downstream casting of data from 25 to 18 bits corrupt only the channel which has saturated. In most cases, this is likely to be RFI.

The suggested configuration of the PFB is therefore as follows:

1. Set the FFT shift schedule to scale by 2^6 (see `fft_set_shift`).
2. Over a long period of integration, verify that no overflows within the FFT are occurring (see `fft_of_detect`).
3. Check for overflows in the downstream data-saturation logic (see `fft_cast_of_detect`).
4. Check power spectra to verify that power-levels are not saturating anywhere near the level of signals-of-interest (see `spec_read`)

Relevant Software Methods

- `fft_set_shift`: Set the FFT shift schedule
- `fft_of_detect`: Count overflows in the FFT module
- `fft_cast_of_detect`: Count overflows downstream of the FFT
- `spec_read`: Read an accumulated spectrum
- `spec_plot`: Plot an accumulated spectrum

1.4.4 Spectral Power Accumulator

The Spectral Power Accumulator generates power-spectra for the two input data streams.

First, the auto- and cross- power of the two input data streams are computed. The former are real-valued, while the latter is complex.

All are computed by:

1. Multiplying 18-bit voltage inputs to generate 36-bit powers
2. Rounding (to even) these 36-bit powers to 25 bits, throwing away the least-significant bits
3. Integrating these powers into 32-bit accumulators, with a runtime-configurable integration length

The nature of the bit handling in this implementation has the following “features”:

1. Discarding the least-significant bits of the signal powers prior to accumulation potentially makes the system vulnerable to degraded performance if the inputs are very low-power. Avoiding excessive downshifting in the PFB can minimize the impact of this effect. Verifying that data output from the accumulators is consistent with reasonable input signal levels (i.e. after dividing out the accumulation length, the resulting value should be $>> 1$) can verify this is not a problem.
2. The accumulators can only guarantee that 128 spectra can be integrated without overflow. This is only ~400 microseconds of data!

In practice, neither of these issues is likely to cause problems, except in the case of very long ($>> 1$ second) integrations.

Spectra can be read from the power accumulator via software – appropriate for monitoring, debugging, and low time-resolution (~1s) observations – or can be streamed out of the SNAP’s 10 GbE interface. The latter interface supports integration lengths of down to 150 micro-seconds, and emits data in the format described in *Spectrometer Packets*.

A test vector injection module exists for the purposes of testing the spectrometer pipeline. When activated, this module replaces PFB data with a test pattern whose real parts are zero, and whose imaginary parts form a counter. For the X-polarization, FFT channel i takes the value $32 * (8 \text{floor}(\frac{i}{4}) + \text{mod}(i, 4))$. For the Y-polarization, FFT channel i takes the value $32 * (8 \text{floor}(\frac{i}{4}) + \text{mod}(i, 4)) + 4$.

Scaling in the spectrometer is such that the test vector inputs appear at the accumulator input with FFT channel i having the values:

- For the X-polarization: $8 * \text{floor}(\frac{i}{4}) + \text{mod}(i, 4)$.
- For the Y-polarization: $8 * \text{floor}(\frac{i}{4}) + \text{mod}(i, 4) + 4$.

This pattern can be checked against observed output data to verify that the two polarizations are being correctly identified, and accumulation length is being correctly set.

- `set_accumulation_length`: Set the number of spectra to be accumulated
- `spec_read`: Read an accumulated spectrum
- `spec_plot`: Plot an accumulated spectrum
- `eth_set_mode`: Choose between spectrometer and voltage 10GbE outputs
- `eth_set_dest_port`: Set the destination UDP port for 10GbE traffic
- `spec_set_destination`: Set the destination IP address for spectrometer packets
- `spec_test_vector_mode`: Turn on and off the spectrometer test-vector mode

1.4.5 Equalization

In the voltage pipeline, post-PFB data are quantized to 4 bits prior to being transmitted over 10 GbE.

Reducing data to such low bit-precision requires carefully managing input signal levels. As such, prior to equalization, spectra are multiplied by a runtime-programmable amplitude scaling factor. The scaling factors can be uniquely specified per polarization and per frequency channel, and should be used to ensure that data in each frequency channel exhibit an appropriate RMS.

Equalization coefficients can be computed by inferring the power levels out of the PFB using the SNAP's inbuilt spectrometer, and computing the necessary scaling required to target an optimal level [quant].

Otherwise, coefficients may be computed by a downstream receiver which has direct access to the 4-bit levels.

TODO: Provide a method to do this, given the scalings, it's non trivial.

- `eq_load_coeffs`: Load a set of equalization coefficients
- TODO: Add method to auto-set.

1.4.6 Voltage Channel Selection

- `select_output_channels`: Select which frequency channels are to be sent over 10 GbE
- `eq_load_test_vectors`: Load a custom set of test vectors into the voltage data path
- `eq_test_vector_mode`: Turn on or off voltage test vector injection

1.4.7 10Gb Ethernet

- `eth_reset`: Reset the Ethernet core
- `eth_set_mode`: Choose between spectrometer and voltage 10GbE outputs
- `eth_set_dest_port`: Set the destination UDP port for 10GbE traffic
- `eth_enable_output`: Turn on 10GbE transmission
- `eth_print_counters`: Print Ethernet packet statistics

1.4.8 Spectral Power Accumulator

1.5 Run-time Control

1.5.1 Installing the Control Library

The *ata_snap* python library is provided to control the F-Engine firmware design. It requires Python ≥ 3.5 and the following custom python libraries:

1. `casperfpga` (a control library for interacting with CASPER hardware, such as SNAP boards)
2. `adc5g` (a library for configuring the ADC5G card)

These libraries are bundled in the *ata_snap* repository to minimize issues with library version compatibility.

To install the control libraries:

```
# Clone the ata_snap repository
git clone https://github.com/realtimeradio/ata_snap

# Clone relevant sub-repositories
cd ata_snap
git submodule init
git submodule update

# Install casperfpga
cd sw/casperfpga
# Install casperfpga dependencies (requires pip, which can be installed with `apt_
↪install python3-pip`
pip install -r requirements.txt
# Install casperfpga
python setup.py install

# Install the adc5g library
cd ../adc5g/adc5g
python setup.py install

# Install the ata_snap library
cd ../../../../ata_snap
python setup.py install
```

If the library has installed correctly, in a Python shell, you should be able to successfully execute

```
from ata_snap import ata_snap_fengine
```

1.6 Configuration Recipes

Simple use of the *ata_snap* library comprises the following steps:

1. Program the SNAP boards with appropriate firmware
2. Configure any runtime settings
3. Synchronize SNAP boards with UTC
4. Turn on data flow

Once these steps are complete, data will be transmitted over Ethernet and downstream software can catch and process this data as desired.

For a single SNAP board, all of these steps can be carried out at once using a provided initialization scrips `snap_feng_init.py`. This script has the following use template:

```
$ snap_feng_init.py -h
usage: snap_feng_init.py [-h] [-s] [-t] [--eth_spec] [--eth_volt] [-a ACCLN]
                        [-f FFTSHIFT] [--specdest SPECDEST]
                        host fpgfile configfile

Program and initialize a SNAP ADC5G spectrometer

positional arguments:
  host                Hostname / IP of SNAP
  fpgfile              .fpgfile to program
  configfile           Configuration file
```

(continues on next page)

(continued from previous page)

```
optional arguments:
  -h, --help            show this help message and exit
  -s                    Use this flag to re-arm the design's sync logic
                        (default: False)
  -t                    Use this flag to switch to post-fft test vector outputs
                        (default: False)
  --eth_spec            Use this flag to switch on Ethernet transmission of the
                        spectrometer (default: False)
  --eth_volt            Use this flag to switch on Ethernet transmission of
                        F-engine data (default: False)
  -a ACCLLEN            Number of spectra to accumulate per spectrometer dump.
                        Default: get from config file (default: None)
  -f FFTSHIFT           FFT shift schedule. Default: get from configuration
                        file (default: None)
  --specdest SPECDEST  Destination IP address to which spectra should be sent.
                        Default: get from config file (default: None)
```

1.6.1 Configuration File

```
fftshift: 0xffffa
acclen: 300000
# Coeffs should be a single number, or an array
# of 4096 numbers to set one coefficient per channel.
coeffs: 100
# UDP port for 10GbE data
dest_port: 10000
spectrometer_dest: 10.11.10.173
# Define which channels should be output
# over 10GbE in voltage dump mode.
voltage_output:
  start_chan: 0
  n_chans: 1024
  # Channels will be spread over the following
  # destinations so that the first n_chans // len(dests)
  # go to the first IP address, etc.
  dests:
    - 10.11.10.173
# All relevant IP/MAC mapping should be manually
# specified here
arp:
  10.11.10.173: 0xaecc7b400ff
  10.11.10.174: 0xaecc7b400a0
```


ATA_SNAP API REFERENCE

```
class ata_snap.ata_snap_fengine.AtaSnapEngine (host, ant_id=0, transport=<class 'casperfpga.transport_tapcp.TapcpTransport'>)
```

Bases: object

This is a class which implements methods for programming and communicating with a SNAP board running the ATA F-Engine firmware.

Parameters

- **host** (*str*) – Hostname of SNAP board associated with this instance.
- **ant_id** (*int*) – Antenna ID of the antenna connected to this SNAP. This value is used in the output headers of data packets.
- **transport** (*casperfpga.Transport*) – The type of connection the SNAP supports. Should be either *casperfpga.TapcpTransport* (if communicating over 10GbE) or *casperfpga.KatcpTransport* (if communicating via a Raspberry Pi)

adc_get_samples ()

Get a block of samples from both ADC inputs.

Returns x, y (numpy arrays of ADC sample values)

Return type numpy.ndarray

adc_initialize ()

Initialize the ADC interface by performing FPGA<->ADC link training. Put the ADC chip in dual-input mode. This method must be called after programming a SNAP, and is called automatically if using this class's *program* method with *init_adc*=True.

eq_load_coeffs (*pol*, *coeffs*)

Load coefficients with which to multiply data prior to 4-bit quantization. Coefficients are rounded and saturated such that they fall in the range (0, 2048), with a precision of $2^{-5} = 0.03125$. A single coefficient can be provided, in which case coefficients for all frequency channels will be set to this value. If an array or list of coefficients are provided, there should be one coefficient per frequency channel in the firmware pipeline.

Parameters

- **pol** (*int*) – Selects which polarization vectors are being loaded to (0 or 1) 0 is the first ADC input, 1 is the second.
- **coeffs** (*float*, or *list* / *numpy.ndarray*) – The coefficients to load. If *coeffs* is a single number, this value is loaded as the coefficient for all frequency channels. If *coeffs* is an array or list, it should have length *self.n_chans_f*. Element [i] of this vector is the coefficient applied to channel i. Coefficients are quantized to UFix16_5 precision.

Raises `AssertionError` – If an array of coefficients is provided with an invalid size, if any coefficients are negative, or if `pol` is a non-allowed value

`eq_load_test_vectors` (*pol*, *tv*)

Load test vectors for the Voltage pipeline test vector injection module.

Parameters

- **`pol`** (*int*) – Selects which polarization vectors are being loaded to (0 or 1) 0 is the first ADC input, 1 is the second.
- **`tv`** (*numpy.ndarray or list of ints*) – Test vectors to be loaded. *tv* should have `self.n_chans_f` elements. `tv[i]` is the test value for channel *i*. Each value should be an 8-bit number - the most-significant 4 bits are interpreted as the 4-bit, signed, real part of the data stream. The least-significant 4 bits are interpreted as the 4-bit, signed, imaginary part of the data stream.

Raises `AssertionError` – If an array of test vectors is provided with an invalid size, or if `pol` is a non-allowed value

`eq_test_vector_mode` (*enable*)

Turn on or off the test vector mode downstream of the 4-bit quantizers. This mode can be used to replace the FFT output in the voltage data path with an arbitrary pattern which can be set with `eq_load_test_vectors`

Parameters `enable` (*bool*) – True to turn on the test mode, False to turn off

`eth_enable_output` (*enable=True*)

Enable the 10GbE output datastream. Only do this after appropriately setting an output configuration and setting the pipeline mode with `eth_set_mode`. For spectra mode, prior to enabling Ethernet the destination address should be set with `spec_set_destination`. For voltage mode, prior to enabling Ethernet configuration should be loaded with `select_output_channels`

Parameters `enable` (*bool*) – Set to True to enable Ethernet transmission, or False to disable.

`eth_print_counters` ()

Print ethernet statistics counters. This is a simple wrapper around `casperfpgas.gbes.read_counters()` method.

`eth_reset` ()

Reset the Ethernet core. This method will clear the reset after asserting, and will leave the transmission stream disabled. Reactivate the Ethernet core with `eth_enable_output`

`eth_set_dest_port` (*port*)

Set the destination UDP port for output 10GbE packets.

Parameters `port` (*int*) – UDP port to which traffic should be sent.

`eth_set_mode` (*mode='voltage'*)

Set the 10GbE output stream to either “voltage” or “spectra” mode. To prevent undesired behaviour, this method will disable Ethernet transmission prior to switching. Transmission should be re-enabled if desired using `eth_enable_output`.

Parameters `mode` (*str*) – “voltage” or “spectra”

Raises `AssertionError` – If mode is not an allowed value

`fft_cast_of_detect` ()

Read the FFT’s cast overflow detection register. Will return True if an overflow has been detected in the last accumulation period. False otherwise. Increase the FFT shift schedule to avoid persistent overflows.

FFT processing pads 18-bit input data with 7 guard bits (to reach 25 bits), performs an FFT with a 25-bit data path, and then throws away the top 7 bits to retain 18 bits of data. In the process of this bit truncation, data may overflow. Unlike an internal FFT overflow, which corrupts an entire spectrum, an overflow during

casting simply corrupts the channel with the overflow. Since this is likely to be a bin containing RFI, this may be acceptable, but you should check the spectrometer spectra to ensure the majority of the spectrum remains intact.

Returns True if post-FFT cast overflowed in the last accumulation period, False otherwise.

Return type bool

fft_of_detect ()

Read the FFT overflow detection register. Will return True if an overflow has been detected in the last accumulation period. False otherwise. Increase the FFT shift schedule to avoid persistent overflows.

Returns True if FFT overflowed in the last accumulation period, False otherwise.

Return type bool

fft_set_shift (*shift=2016*)

Set the FFT shift pattern. The firmware interprets the shift value as a binary value, with each bit controlling the shift (divide-by-two) at one stage of the FFT. The number of stages in the FFT is equal to $\log_2(\text{FFT_SIZE})$.

Example usage: `fft_set_shift(2**13-1)` : Shift down every stage of an 8k-point FFT `fft_set_shift(0b11)` : Shift down on the first two stages of the FFT only `fft_set_shift(0)` : Don't shift at any stage of the FFT

The necessity for shifting depends on the input power levels into the FFT, the number of bits in the FFT data path, and the nature of the input signal. Sinusoidal input signals grow by a factor of 2 at each FFT stage, and therefore might need to be shifted every stage. Noise-like signals grow by a factor of $\sqrt{2}$ at each FFT stage, and therefore might only need to be shifted every other stage. Setting the FFT shift should be done in concert with monitoring the FFT overflow state with `fft_of_detect`.

NB: in firmware versions ≥ 1.02 the FFT input data are padded by 7 bits. For an 8192 point transform, this means 6 bits of shifting is sufficient to avoid overflow.

Parameters **shift** (*int*) – Shift schedule

is_programmed ()

Returns True if the fpga appears to be programmed with a valid F-engine design. Returns False otherwise. The test this method uses is searching for the register named *fversion* in the running firmware, so it can easily be fooled. :return: True if programmed, False otherwise :rtype: bool

program (*fpgfile, force=False, init_adc=True*)

Program a SNAP with a new firmware file.

Parameters

- **fpgfile** (*str*) – .fpg file containing firmware to be programmed
- **force** (*bool*) – If True, overwrite the existing firmware even if the firmware to load appears to already be present. This only makes a difference for *TapcpTransport* connections.
- **init_adc** (*bool*) – If True, initialize the ADC cards after programming. If False, you *must* do this manually before using the firmware using the `adc_initialize` method.

select_output_channels (*start_chan, n_chans, dests=['0.0.0.0']*)

Select the range of channels which the voltage pipeline should output.

Example usage:

Send channels 0..255 to 10.0.0.1: `select_output_channels(0, 256, dests=['10.0.0.1'])`

Send channels 0..255 to 10.0.0.1, and 256..512 to 10.0.0.2 `select_output_channels(0, 512, dests=['10.0.0.1', '10.0.0.2'])`

Parameters

- **start_chan** (*int*) – First channel to output
- **n_chans** (*int*) – Number of channels to output
- **dests** (*list of str*) – List of IP address strings to which data should be sent. The first $n_chans / \text{len}(\text{dests})$ will be sent to `dest[0]`, etc..

Raises AssertionError – If the following conditions aren't met: *start_chan* should be a multiple of `self.n_chans_per_block` (16) *n_chans* should be a multiple of `self.n_chans_per_packet` (256) *n_chans* should be \leq `self.n_chans_out` (2048)

set_accumulation_length (*acclen*)

Set the number of spectra to accumulate for the on-board spectrometer.

Parameters acclen (*int*) – Number of spectra to accumulate

spec_plot (*mode='auto'*)

Plot an accumulated spectrum using the matplotlib library. Frequency axis is inferred from the ADC clock frequency detected with `sync_get_adc_clk_freq`.

Parameters mode (*str*;) – “auto” to plot a power spectrum from the X and Y polarizations on separate subplots. “cross” to plot the magnitude and phase of a complex-valued cross-power spectrum of the two polarizations.

Raises AssertionError – if mode is not “auto” or “cross”

spec_read (*mode='auto'*)

Read a single accumulated spectrum.

Parameters mode (*str*;) – “auto” to read an autocorrelation for each of the X and Y pols. “cross” to read a cross-correlation of `Xconj(Y)`.

Raises AssertionError – if mode is not “auto” or “cross”

Returns If mode=“auto”: A tuple of two numpy arrays, `xx`, `yy`, containing a power spectrum from the X and Y polarizations. If mode=“cross”: A complex numpy array containing the cross-power spectrum of `Xconj(Y)`.

Return type `numpy.array`

spec_set_destination (*dest_ip*)

Set the destination IP address for spectrometer packets.

Parameters dest_ip (*str*) – Destination IP address. E.g. “10.0.0.1”

spec_test_vector_mode (*enable*)

Turn on or off the test vector mode in the spectrometer data path. This mode replaces the FFT output in the data path with 12 bit counter which occupies the most significant bits of the imaginary part of the FFT output. I.e. when enabled, the imaginary part of each spectrum is a ramp from $0..4095 / 2^{*17}$

Parameters enable (*bool*) – True to turn on the test mode, False to turn off

sync_arm ()

Arm the FPGA's sync generators for triggering on a subsequent PPS. The arming procedure is the following: 1. Wait for a PPS to pass using `sync_wait_for_pps`. 2. Arm the FPGA's sync register to trigger on the next+2 PPS 3. Compute the time this PPS is expected, based on this computer's clock. 4. Write this time as a 32-bit UNIX time integer to the FPGA, to record the sync event.

Returns Sync trigger time, in UNIX format

Rval `int`

sync_get_adc_clk_freq ()

Infer the ADC clock period by counting FPGA clock ticks between PPS events.

Returns ADC clock rate in MHz

Rval float

sync_get_ext_count ()

Read the number of external sync pulses which have been received since the board was last programmed.

Returns Number of sync pulses received

Rval int

sync_get_fpga_clk_pps_interval ()

Read the number of FPGA clock ticks between the last two external sync pulses.

Returns FPGA clock ticks

Rval int

sync_get_last_sync_time ()

Get the sync time currently stored on this FPGA

Returns Sync trigger time, in UNIX format

Rval int

sync_wait_for_pps ()

Block until an external PPS trigger has passed. I.e., poll the FPGA's PPS count register and do not return until is changes.

INDEX

- genindex
- modindex
- search

BIBLIOGRAPHY

- [e2v] e2v EV8AQ160 datasheet (https://www.teledyne-e2v.com/content/uploads/2019/10/EV8AQ160_0846K.pdf)
- [hmcad1511] Analog Devices HMCAD1511 datasheet (<https://www.analog.com/media/en/technical-documentation/data-sheets/hmcad1511.pdf>)
- [casper_snap] See https://github.com/casper-astro/casper-hardware/blob/master/FPGA_Hosts/SNAP/README.md
- [casper_adc5g] See <https://casper.ssl.berkeley.edu/wiki/ADC1x5000-8>
- [rpi] See <https://www.raspberrypi.org/products/raspberry-pi-2-model-b>
- [pfb] Price, D; Spectrometers and Polyphse Filterbanks in Radio Astronomy; 2016; <https://arxiv.org/abs/1607.03579>
- [quant] Thompson, A et al.; Convenient Formulas for Quantization Efficiency; 2007; <https://agupubs.onlinelibrary.wiley.com/doi/full/10.1029/2006RS003585>

PYTHON MODULE INDEX

a

`ata_snap.ata_snap_fengine`, [15](#)

INDEX

A

`adc_get_samples()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 15

`adc_initialize()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 15

`ata_snap.ata_snap_fengine`
module, 15

`AtaSnapFengine` (class
ata_snap.ata_snap_fengine), 15

E

`eq_load_coeffs()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 15

`eq_load_test_vectors()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`eq_test_vector_mode()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`eth_enable_output()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`eth_print_counters()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`eth_reset()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`eth_set_dest_port()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`eth_set_mode()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

F

`fft_cast_of_detect()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 16

`fft_of_detect()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 17

`fft_set_shift()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 17

I

`is_programmed()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 17

M

module
ata_snap.ata_snap_fengine, 15

P

`program()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 17

S

`select_output_channels()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 17

`set_accumulation_length()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`spec_plot()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`spec_read()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`spec_set_destination()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`spec_test_vector_mode()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`sync_arm()` (*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`sync_get_adc_clk_freq()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 18

`sync_get_ext_count()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 19

`sync_get_fpga_clk_pps_interval()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 19

`sync_get_last_sync_time()`
(*ata_snap.ata_snap_fengine.AtaSnapFengine*
method), 19

```
        method), 19  
sync_wait_for_pps()  
    (ata_snap.ata_snap_fengine.AtaSnapFengine  
    method), 19
```